LULU STEP-BY-STEP GUIDE

Customize the Quick view button and pop-up (QuickPeek)

For store owners: turn on Quick view on your product cards and restyle the button and the pop-up — text, style, position, colours, width, photo position, corners, animation and which details show — from the theme editor.

For: Everyone · About 7 minutes · 6 steps · Updated November 20, 2026

Before you start You need the QuickPeek Quick View app installed. Styling the button and pop-up takes effect on the Growth plan or higher; on the Free plan it takes effect only while your store is still a development store. On any other plan the store keeps the default Quick view look — you can still open and preview the settings. Every setting starts at its default, which keeps today's look, so nothing changes until you change it.

Steps at a glance

1. Turn Quick view on
2. Rename and restyle the button
3. Style the pop-up
4. Choose which details show
5. Pick a layout (QuickPeek Pro)
6. Save and check your store

STEP 1

Turn Quick view on

In your admin go to Online Store → Themes and open the theme editor with Customize. Open the Collection page and select the "Collection banner & grid" settings. In the Product cards group, tick "Show a “Quick view” button". Pointing at a product card now reveals a Quick view button that opens the product in a pop-up; the card itself still goes to the full product page.

- The extra settings below only appear in the Quick view group; the layout picker only appears once Quick view is on.

STEP 2

Rename and restyle the button

In the "Quick view" group set the button. "Button text" is blank by default, which shows "Quick view" (translated for your shoppers); you can type your own, up to 24 characters. "Button style" is "Solid (default)", "Outline" or "Icon only". "Button position on the card" is "Centre of the photo (default)", "Bottom centre", "Bottom left", "Bottom right", "Top left" or "Top right".

- "Button colour" overrides the theme's button colour; leave it blank to keep the theme's. The text colour adjusts automatically so it stays readable.

STEP 3

Style the pop-up

Set the pop-up's look: "Pop-up accent colour" (sale price, selected size, vendor line and links; blank uses the theme accent), "Pop-up width" (Small, Medium (default), Large), "Photo position" (Photo on the left (default), Photo on the right, Photo on top), "Corner radius" (Theme default, Square, Small, Medium, Large), "Background darkness" (Light, Medium (default), Dark, Darkest) and "Open animation" (Fade and rise (default), Fade, Slide up, None).

STEP 4

Choose which details show

Tick or untick: "Show vendor" and "Show quantity selector" and "Show “View full details” link" (all on by default), and "Show star rating", "Show a short description" and "Show SKU" (off by default).

- Products with no reviews show no star rating even when "Show star rating" is on.

STEP 5

Pick a layout (QuickPeek Pro)

"Quick view layout" offers Centered modal (default), Side drawer, Bottom sheet, Split media / details, Gallery-first and Minimal. This is a separate QuickPeek Pro feature: on other plans the pop-up always uses the centered modal, whatever is picked.

- The Quick view styling settings above work on Growth and Pro. The layout picker needs the Pro plan.

STEP 6

Save and check your store

Save the theme (and publish if you are editing a draft), then open your live store and point at a product card. If the look did not change, see the plan notes below.

- You can undo a change by setting the field back to its default, or leaving it blank.

Check your work

- Show a “Quick view” button is ticked.
- The QuickPeek app is installed and your plan is Growth or higher (or a development store on Free).
- The button and pop-up look right on both a phone and a desktop screen.
- Layout choices other than the centered modal are only expected if you are on QuickPeek Pro.

Troubleshooting

I changed the settings but my live store looks the same.

Styling takes effect on the Growth plan or higher, or on the Free plan only while the store is a development store. On other plans, or if the QuickPeek app is not installed, the store keeps the default look. Upgrade the app plan in the App Store.

Do I lose my settings if I am on a lower plan?

The values stay saved in the theme editor; they are simply not applied to your storefront until your plan allows them.

Where is the Quick view group?

In the theme editor, on the Collection page template, in the "Collection banner & grid" settings. If you do not see it, check that the QuickPeek Quick View app is installed.

The layout setting does nothing.

Layouts other than the Centered modal need the QuickPeek Pro plan; other plans always use the centered modal.

Can I use any colour?

Use a normal hex colour such as #1a2b3c. Anything else is ignored and the theme colour is used.

My button text is cut off.

The text is limited to 24 characters. Shorten it or choose "Icon only".

Need a hand? Contact support at https://lulu.us.com/contact. Screenshots use demonstration accounts; personal details were replaced.